

MCImetro Access Transmission Services Corp.
d/b/a Verizon Access Transmission Services

New York Tariff No. 1
Original Page No. 62

ACCESS SERVICES

5. SWITCHED ACCESS SERVICE

5.1 General

Switched Access Service, which is available to Customers for their use in furnishing their services to End Users, provides a two-point communications path between a Customer's Premises and an End User's Premises. It provides for the use of common terminating, switching and transport facilities. Switched Access Service provides the ability to originate calls from an End User's Premises to a Customer's Premises, and to terminate calls from a Customer's Premises location to an End User's Premises.

Rates and charges are set forth in Section 7.4. The application of rates for Switched Access Service is described in Section 7.2.

5.2 Provision and Description of Switched Access Service Arrangements

Switched Access Service is provided in the following service type:

5.2.1 Feature Group D (FGD) Access

FGD Access, which is available to all Customers, is provisioned at the DS1 level and provides trunk-side access to Company Local Switching Center switches, with an associated uniform 1010XXX Access Code for the Customer's use in originating and terminating communications. Basic FGD service will be provided with Multi-Frequency In Band Signaling (SS7 is also available as a Common Switching Option for Feature Group D). In addition, Conventional Signaling for direct Carrier Trunk groups is available at the Customer's option. End Users of the Customer's service may also originate calls to certain FGD Access Customers without dialing the 10XXX Access Code if the End User is presubscribed, as described herein.

The Access Code for FGD switching is a uniform Access Code of the form 10XXX. A single Access Code will be the assigned number of all FGD access provided to the Customer by the Company. No Access Code is required for calls to a Customer over FGD Switched Access Service if the End User's telephone exchange service is arranged for Presubscription to that Customer, as set forth herein.

Where no Access Code is required, the number dialed by the Customer's End User shall be a seven or ten digit number for calls in the North American Numbering Plan (NANP), except for 00- dialed calls which are routed to the predesignated Customer. For international calls outside the NANP, a seven to twelve digit number may be dialed. The form of the numbers dialed by the Customer's End User is NXX-XXXX, 0 or 1 + NXX-XXXX, NPA + NXX-XXX, 0 or 1 + NPA + NXX-XXXX, and, when the Local Switching Center is equipped for International Direct Distance Dialing (IDDD), 01 + CC + NN or 011 + CC + NN.

When the 10XXX Access Code is used, FGD switching also provides for dialing the digit 0 for access to the Customer's operator, 911 for access to the Company's emergency service, or the end-of-dialing digit (#) for cut-through access to the Customer's Premises.